

How to work with Bacillus subtilis vectors

There are some features in *B. subtilis* vectors that have to be taken into account, while working with them.

- Cloning in *E. coli*
- Linearisation before *B. subtilis* transformation
- Verification of integration

Pre-Cloning in *E. coli*

The cloning, that means the insertion of your part into the multiple cloning site, is done with normal ligations and *E. coli*. However, since the *B. subtilis* vectors are quite large, the cloning works best if only one insert is inserted. You could try to finish your construct in e.g. pSB1C3 and then clone it into the *B. subtilis* vector. For convenience, all vectors carry an RFP with promoter and terminator which is substituted by your insert during the ligation (Part: BBa_I732017).

Our vectors all carry the *bla* gene that mediates Ampicillin resistance (100µg/ml) in *E. coli*. Also, they all have two recombination sites to result in a double crossover in a designated locus. In between those recombination sites, there is the multiple cloning site and a resistance marker for *B. subtilis*.

[Some vectors from other working groups do not carry an extra *E. coli* resistance, so the *B. subtilis* resistance is also used in *E. coli* but with lower antibiotic concentrations. There also is the possibility of single-crossover plasmids which do also work fine, but the vector can then easily cross-out again, so it is not stably integrated.]

Linearisation before transformation in *B. subtilis*

Nevertheless, the obtained plasmid (if it is not replicative) has to be linearized before transformation. *B. subtilis* is naturally competent, but preferably takes up and integrates linear DNA fragments. The linearization of our plasmids can all be performed with **ScaI** which only cuts inside the *bla* gene. If that enzyme also cuts in your insert, please check for other single cutters outside of the area that is integrated into the *B. subtilis* genome.

For the actual transformation of *B. subtilis*, please linearize 1-2 µg of your plasmid and then proceed with our transformation protocol.

Verification of correct integration

To check if the plasmid was taken up, the transformed *B. subtilis* is plated on selective media, LB with the appropriate antibiotic (resistance gene in between recombination sites). The obtained colonies then are tested for their insertion into the correct locus. Usually it is sufficient to test 4-8 colonies.

To test the insertion into the

- **amyE-locus:** streak the obtained colonies (and the WT as control) on a replica plate (with antibiotic) and on a starch plate and let grow overnight at 37°C. The next day, pour Lugols solution (Iod-iodine-potassium?) on the plate so that it is covered with a thin film. Around colonies which can degrade starch (WT and wrong colonies), there should be a bright zone around the colony. Correct clones do not show this bright zone (see also picture)

- ***thrC*-locus**: streak the obtained colonies (and the WT as control) on a replica plate (with antibiotic) and on a plate with minimal medium without threonine and minimal medium with threonine (use the MNGE media, recipe see transformation protocol). Correct colonies should grow only on the LB and minimal medium with threonine plate.
- ***sacA*-locus and *lacA*-locus**: for those two loci, a colony PCR should be performed. For *sacA* you can use the primers:
- **for *lacA*, you can use the primers**: TM2505+06 and TM2507+08
- **With colony PCR you can check any other locus.**